



Checkpoint SmartDashboard R77 - PSM

Description

Connect securely to Checkpoint SmartDashboard Console

Vendor

This connection component is designed for secure connection to the following target:

Vendor	Checkpoint
Product	SmartDashboard Console
Product Category	Security Appliance
Product Versions	R77

CyberArk

This connection component works with the following CyberArk versions:

CyberArk Solution	Privileged Session Management
CyberArk Product	Privileged Session Manager (PSM)
CyberArk Versions	9.7 or higher
Artifact Version	1.0
Out of the Box	NO
Out of the Box in versions	



- Business Confidential -

Support & Certification

Developed by	Bulwarx Ltd.
Certification Level	Community

Prerequisites

The following prerequisites are required on the machine that will run this connection component :

- An installation of the Checkpoint SmartDashboard R77 software is required on all PSM servers
- Installation of Autolt on all required PSM servers
- Transfer the Autolt connection script to the PSM components folder.
Default path: C:\Program Files (x86)\CyberArk\PSM\Components

Configuration

Connection Component Settings

Specify the following parameters at the connection component level:

Connection Component Root Level Parameters

Parameters that define generic settings of the PSM connection component.

Parameter Name	Description	Acceptable Values	Default Value
Id	A unique ID that identifies the connection component	String	PSM-CheckpointSD
DisplayName	The name to be displayed in the connection selection.	String	Checkpoint SmartDashboard



- Business Confidential -

Target Settings section

Parameters that define specific target machines settings. These parameters can be overridden at platform or account level.

Client Specific

Parameter Name	Description	Acceptable Values	Default Value
Protocol	Target connection protocol. This value is not used but needs to be filled	Anything	Checkpoint
ClientApp	Relevant only to command line clients. This value is not used but needs to be filled	Anything	Dummy.exe
ClientDispatcher	The internal client that will open the target connection	Full path	"C:\Program Files (x86)\Autolt3\Autolt3.exe" "{PSMComponentsFolder}\PSM-SmartDashboard-R70.au3" "{PSMComponentsFolder}"
ClientInvokeType	The connection client invocation method. This method will be used for invoking the connection client, and passing it all the required parameters.		Dispatcher
ConnectionComponentInitTimeout	Time allowed for the connection component to initialize, in milliseconds. 0 means infinitely.	Numeric value	20000



- Business Confidential -

Autolt Settings

Parameter Name	Description	Acceptable Values	Default Value
\$PROGRAM_NAME	Program title	Text	"Check Point SmartDashboard"
\$PROGRAM_TITLE	The dispatcher process name.	Text	"Check Point SmartDashboard"
\$PROGRAM_VERSION	Checkpoint version	Text + Numeric	"77.30"
\$CLIENT_EXECUTABLE	Location of the smartdashboard executable file	Full Path	"C:\Program files (x86)\CheckPoint\SmartConsole\R77.30\PROGRAM\CPAppStart.exe"