



Fortinet Fortigate Plug-in for the Central Policy Manager

The Cyber-Ark Password Vault
Version 12.x

Copyright © 2025 CyberArk Software Ltd. All rights reserved.

This document contains information and ideas, which are proprietary to CyberArk Software Ltd. No part of this publication may be reproduced, stored in a retrieval system, or transmitted, in any form or by any means, electronic, mechanical, photocopying, recording, scanning, or otherwise, without the prior written permission of CyberArk Software Ltd.

EPVEMC07-2-0-1



Changing Passwords on Fortinet Fortigate

The Central Password Manager enables organizations to change passwords automatically on remote machines and store the new passwords in the Enterprise Password Vault, with no human intervention, according to the organizational policy. This plug-in supports the changing of passwords for admin users** on the Fortinet Fortigate using the SSH protocol.

** (accprofile "super_admin")

Prerequisite


This plugin runs on the Terminal Plugin Controller (TPC) engine. It can be found on the Marketplace [here](#).

Installation

You will receive the FortinetFGT plug-in zip archive from your CyberArk representative. The following instructions show you how to install it.

Installing the Fortinet Fortigate Plug-in

1. Log in to the PVWA with an administrative account.
2. Go to Administration > Platform Management.
3. Click Import Platform. Upload the FortinetFGTPlugin.zip file.



Platform Configuration

- Please check that the following default platform settings match your environment.
- They can be modified by navigating to Administration → Platform Management → FortinetFGT → Edit → Automatic Password Management → Additional Policy Settings

Parameter Name	Description	Value
Protocol	The protocol used to connect to the target device.	SSH
Port	The port used to connect to the target device.	22

Adding FortinetFGT Accounts

Adding Accounts through the Password Vault Web Access

- Create a new FortinetFGT account or use an existing one.
- Specify the required account properties.
- If required, associate a reconcile account for the new password object

For more information about adding password objects in the Password Vault Web Access, refer to the online documentation [here](#).

General Notes

FortinetFGT plug-in supports the following:

- Password change
- Password verification
- Password reconciliation