



Cohesity Cluster OS Plug-in for the Central Policy Manager

The CyberArk Password Vault
Version 12.x

Copyright © 1999-2026 CyberArk Software Ltd. All rights reserved.

This document contains information and ideas, which are proprietary to CyberArk Software Ltd. No part of this publication may be reproduced, stored in a retrieval system, or transmitted, in any form or by any means, electronic, mechanical, photocopying, recording, scanning, or otherwise, without the prior written permission of CyberArk Software Ltd.

EPVEMC07-2-0-1



Changing Passwords on Cohesity Cluster OS

The Central Password Manager enables organizations to change passwords automatically on remote machines and store the new passwords in the Enterprise Password Vault, with no human intervention, according to the organizational policy. This plug-in supports the changing of passwords for users on the Cohesity Cluster OS using the REST API protocol.

Installation

You will receive the CohesityClusterOS plug-in zip archive from your CyberArk representative. The following instructions show you how to install it.


Pre-requisites

Download and install the [REST API Platform](#) from Marketplace

If you already have an older version installed, remove the platform and install the newest version from Marketplace

Installing the Cohesity Cluster OS Plug-in

1. Log in to the PVWA with an administrative account.
2. Go to Administration > Platform Management.
3. Click Import Platform. Upload the CohesityClusterOSPlugin.zip file.



Platform Configuration

- Please check that the following default platform settings match your environment.
- They can be modified by navigating to Administration -> Platform Management -> CohesityClusterOS -> Edit -> Automatic Password Management -> Additional Policy Settings

Platform Parameter	Description	Value
SSHPort	The port used to connect to the remote machine	22

Adding CohesityClusterOS Accounts

Adding Accounts through the Password Vault Web Access

- Create a new CohesityClusterOS account or use an existing one.
- Specify the required account properties.

Platform Parameter	Description	Value
Username	The port used to connect to the remote machine	
Address	Address of the Cohesity Cluster DataPlatform web server	

For more information about adding password objects in the Password Vault Web Access, refer to the online documentation [here](#).



General Notes

CohesityClusterOS plug-in supports the following:

- Password change
- Password reconcile
- Password verification