



Dell Unisphere PowerMax Plug-in for the Central Policy Manager

The Cyber-Ark Password Vault
Version 12.x

Copyright © 1999-2026 Cyber-Ark Software Ltd. All rights reserved.

This document contains information and ideas, which are proprietary to Cyber-Ark Software Ltd. No part of this publication may be reproduced, stored in a retrieval system, or transmitted, in any form or by any means, electronic, mechanical, photocopying, recording, scanning, or otherwise, without the prior written permission of Cyber-Ark Software Ltd.

EPVEMC07-2-0-1



Changing Passwords on Dell Unisphere PowerMax

The Central Password Manager enables organizations to change passwords automatically on remote machines and store the new passwords in the Enterprise Password Vault, with no human intervention, according to the organizational policy. This plug-in supports the changing of passwords for users on the Dell Unisphere PowerMax using the REST API protocol.

Installation

You will receive the DellUnispherePowerMax plug-in zip archive from your CyberArk representative. The following instructions show you how to install it.


Pre-requisites

Download and install the [REST API Platform](#) from Marketplace

If you already have an older version installed, remove the platform and install the newest version from Marketplace

Installing the Dell Unisphere PowerMax Plug-in

1. Log in to the PVWA with an administrative account.
2. Go to Administration > Platform Management.
3. Click Import Platform. Upload the DellUnispherePowerMaxPlugin.zip file.



Platform Configuration

- Please check that the following default platform settings match your environment.
- They can be modified by navigating to Administration → Platform Management → DellUnispherePowerMax → Edit → Automatic Password Management → Additional Policy Settings → Parameters

Parameter Name	Description	Value
UseSSL	Setting this property to yes will create a REST API request using HTTPS and validate a proper certificate is used. Setting this property to no will create a REST API request using HTTP. Setting this property to ignoreuntrustedcertificates will create a REST API request using HTTPS but does not require a valid certificate.	Yes
Port	The port used to connect to the target device. -1 denotes no port to be added to the server in the URL, using the default port for the protocol (443 for https)	-1

Adding DellUnispherePowerMax Accounts

Adding Accounts through the Password Vault Web Access

- Create a new DellUnispherePowerMax account or use an existing one.
- Specify the required account properties.

For more information about adding password objects in the Password Vault Web Access, refer to the online documentation [here](#).

General Notes

DellUnispherePowerMax plug-in supports the following:

- Password change
- Password verification

