



Infinidat Infiniguard Plug-in for the Central Policy Manager

The Cyber-Ark Password Vault
Version 10.x

Copyright © 1999-2018 Cyber-Ark Software Ltd. All rights reserved.

This document contains information and ideas, which are proprietary to Cyber-Ark Software Ltd. No part of this publication may be reproduced, stored in a retrieval system, or transmitted, in any form or by any means, electronic, mechanical, photocopying, recording, scanning, or otherwise, without the prior written permission of Cyber-Ark Software Ltd.

EPVEMC07-2-0-1



Changing Passwords on Infinidat Infiniguard


The Central Password Manager enables organizations to change passwords automatically on remote machines and store the new passwords in the Enterprise Password Vault, with no human intervention, according to the organizational policy. This plug-in supports the changing of passwords for users on the Infinidat Infiniguard using the REST protocol.

Installation

You will receive the InfinidatInfiniguardPlugin.zip archive from your CyberArk representative. The following instructions show you how to install it.

Installing the Infinidat Infiniguard Plug-in

1. Log into the PVWA with an administrative account.
2. Go to Administration > Platform Management.
3. Click Import Platform. Upload the InfinidatInfiniguardPlugin.zip file.



Platform Configuration

- The following platform settings are given initial default values. Please check that these match your environment or edit them accordingly .

To Edit these values navigate to :

Administration → Platform Management → Infinidat Infiniguard → Edit → Automatic Password Management → Additional Policy Settings → Parameters :

Parameter name	Default value	Description
ChainsFilePath	bin\InfinidatInfiniguardChains.xml	Configuration file of REST call logic

To Edit these values navigate to :

Administration → Platform Management → Infinidat Infiniguard → Edit → Automatic Password Management → Additional Policy Settings :

Parameter name	Default value	Description
Port	(empty)	Port to use in URL/s for password management
UseSSL	Yes	Yes – Use https with the URL/s No - Use http with the URL/s IgnoreUntrustedCertificate – Use https, but ignore untrusted certificate
Debug	No	Whether to create a debug log. Useful for troubleshooting.



Adding VMWareCloudFoundations Accounts

Adding Accounts through the Password Vault Web Access

- Create a new VMWareCloudFoundations account or use an existing one.
- Specify the required account properties.
- If required, associate a reconcile account for the new password object

For more information about adding password objects in the Password Vault Web Access, refer to the Privileged Account Security Implementation Guide.

General Notes

Infinidat plug-in supports the following:

- Password verification
- Password change
- Reconciliation

